

GasCom

Release Notes

Version 1.3.4 (02.02.2026)

- Access to Hermann Sewerin GmbH's SFTP server adapted

Version 1.3.3 (10.12.2025)

- Various minor bugs fixed
- Error when loading languages corrected
- Device interface adapted; FTDI driver changes saved: Access enabled to devices that communicate with the most recent FTDI driver

ATS 5xx / EX-TEC PM 5xx/400

- User management: error fixed when retroactively changing and saving a user from the database without a PIN

Version 1.3.2 (30.04.2025)

- Various minor bugs fixed

ATS 5xx

- Device information: error when displaying the checkbox "Display can pressure" fixed
- Protocols: error when reading the protocols of an ATS with firmware ≤ 1.022 fixed
- Firmware update function expanded to include higher firmware versions

ATS 5xx / EX-TEC PM 5xx/400

- Device protocols: filter option for the accrual date implemented
- Error when saving templates fixed; language was incorrectly assigned

Version 1.3.1 (16.10.2024)

- Protocols from the database: loading of the protocols accelerated

ATS 5xx

- Protocols: deletion of a PM subfolder including all contained protocols from the ATS protocol memory enabled ("Delete device in ATS" button)

EX-TEC PM 5xx/400

- Settings ("Alarms")

- For CO, the alarm thresholds “Alarm 1” and “LTEL” have been corrected from 30 ppm to 20 ppm according to TRGS 900 (2024)
- Alarm thresholds corrected when activating only one flammable gas (without CH₄ and C₃H₈)
- Settings (“General I”): languages sorted alphabetically

EX-TEC VARIOTEC

- Protocols from the database, course of single measurements: display error in the curve fixed by using the unit ppm/vol% instead of the unit ppb/vol%

Version 1.3.0 (26.02.2024)

- Protocols:
 - “Warning ECO” application added
 - Access to archived protocols
 - “Inspector” and “Result” columns added
- Database:
 - New function: archive database
 - Monitoring of the database size implemented
- Help/manual:
 - New German version included, as well as English, French, Spanish, Polish and Portuguese
 - For selected dialogs/windows: calling up the Help function via F1 set up
- Updated licence texts

ATS 5xx

- New function: search for / install ATS firmware update
- Device information: “Date/time” column added to error list

ATS 5xx / EX-TEC PM 5xx/400

- User management: deleting “Guest” user disabled
- Error when assigning test gas ExCox IR to the gas file fixed
- Error when loading the user files fixed
- File transfer between device and database revised
- For ATS and PM from firmware version 1.100: window “Manage protocols of selected device” revised

EX-TEC PM 5xx/400

- New function: delete error file entries
- New functions for PM from firmware version 1.100: set key lock, automatic recording, automatic deletion of the oldest recordings / device inspection when memory is full
- Error when reading the device date corrected

- PDF of device inspections revised: summarised for zero-point measurement of CxHy gases

EX-TEC HS, Multitec, VARIOTEC

- File transfer between device and database revised

Version 1.1.8105.24279 (11.03.2022)

- Version query for new setup files revised
- GasCom manual (German) included
- File names changed when exporting files from the database (serialnumber_date_time_filename.xxx)
- Update with limited user rights: incorrect user information corrected

ATS 5xx / EX-TEC PM 5xx/400

- For ATS and PM from firmware version 1.010: test gas CH₄ 100% vol. also approved for use with “Warning” application. (For devices with firmware version below V1.010, the test gas CH₄ 100% vol. is only approved for the “Measuring” application).
- User management: number of maximum and already created users displayed
- Error when activating new gas types fixed

ATS 5xx / EX-TEC PM 400

- Test gas C₃H₈ 0.3% vol. set up for inspection of nonane for all gas connections and for the “Warning” and “Structure” applications
- Prompt when transferring altered device data/settings when switching windows implemented

EX-TEC HS 6xx

- Error when loading “device.cfg” file to display the measurement settings fixed

ATS 5xx

- List of default gases updated

Version 1.1.8048.14745 (13.01.2022)

- New interface 5.4.0.8019 incorporated
- Printing of licence terms and release notes implemented
- Export of selected measurements as *.pdf file to any location (local/network) implemented
- Deletion of temporary files before download of new files implemented
- Error when transferring user logo fixed (e.g. error F52 [XFlash])
- Database error when loading protocol table fixed
- Maximum length and permissible characters for test gas names corrected
- Error when displaying decimal places in alarm values fixed

ATS 5xx

- Communication error with connected test set fixed
- Assignment of gas connections when collating the gas file corrected

ATS 5xx / EX-TEC PM 5xx/400

- CRC inspection – error when reading and writing files fixed
- User management: deleting selected users permitted
- User management: error when deleting name fixed

EX-TEC PM 5xx/400

- Activation/deactivation of gas types corrected
- Error when setting concentration-dependent signal fixed
- Measurement protocol display: error when loading measurement protocols fixed
- Error when collating data for file export fixed
- Error when rounding measurement values for long-term measurements fixed
- Protocol from device inspection (Fxx.prt): display of gases for the zero point changed