

SeGIS TMS

Release Notes

Version 1.3.6 (29.01.2026)

- User rights adapted
- Access to Hermann Sewerin GmbH's SFTP server adapted

Version 1.3.5 (18.12.2025)

- User rights adapted
- Error when starting software corrected: One of the folders required by the software was not found.
- Device interface adapted; FTDI driver changes saved: Access enabled to devices that communicate with the most recent FTDI driver

SePem® 351

- Error when subsequently reading device data after the writing process corrected

LGP 800/900

- The LGP 800 Interface can now be used to incorporate the LGP 900.

Version 1.3.4 (28.10.2025)

- User rights adapted

ATS 501/503

- Error with parameters corrected

FERROPHON® FG 150, 150C, 155C

- Firmware updated (to Version 1.100)

Multitec® 560

- Certificate: Error when reading the adjustment date for the H2S sensor corrected

EX-TEC® HS 680/650, VARIOTEC 450/480, Multitec 520/560

- Button added to lower the CO alarm value from 30 to 20 ppm

SePem® 352/352 HY

- Encryption and decryption of SePem 352 / SePem 352 HY added

EX-TEC® PM 5xx/400

- Error when loading adjustment file history corrected

Version 1.3.3 (18.02.2025)

- User rights adapted
- Password: Security check of password when changed added

SePem® 150 HY

- Device added

SePem® 352 / 352 HY

- Device added

SePem® 35x

- LoRaWAN join component updated

ATS 501/503

- Firmware updated (to Version 1.103)

Version 1.3.2 (30.09.2024)

- User rights adapted

EX-TEC® HS 680/650, VARIOTEC® 480 EX/480 EX and Multitec® 520/560

- ECGasDB changes as per TRGS 900 2024 (Technical Rules for Hazardous Substances) prior to backup

Multitec® 540/545

- Firmware updated (to Version 1.406)

ATS 501/503

- Firmware updated (to Version 1.101)

Version 1.3.1 (21.06.2024)

- Device interface updated (Version 1.1.20)

EX-TEC PM 5xx/400

- Error corrected when updating firmware from Version < 1.010 to Version 1.1.0.0

Version 1.3.0 (16.05.2024)

- Versioning adapted
- Password encryption of user passwords enhanced
- Error corrected when sending “forgotten” passwords via email
- Error corrected when loading release notes
- Error corrected when displaying the release notes stored on the server

EX-TEC PM 5xx/400

- Poll added for the reason behind changing a sensor
- Report adapted to simplify the change, uninstallation and installation of a sensor
- File explorer: Filter option added
- Correction of the alarm threshold for LTEL (CO) from 30 ppm to 20 ppm as per TRGS 2024 in the backup script

SePem® 361

- Status evaluation edited

COMBIPHON® CG 150/155

- Device activated

EX-TEC® HS 680/660/650/610

Multitec® 520

- IR sensor change via barcode implemented

EX-TEC® HS 680/660/650/610

VARIOTEC® 480 EX/460 EX/EGA/400 EX/450 EX

Multitec® 520/410

- Firmware updated (to Version 2.010)
- File explorer: Filter added

ATS 501/503

- Error when loading device inspections for an ATS corrected
- File explorer: Filter option added

LGP 800 Interface module

- Error when assigning a serial number corrected

SePem® 35x

- Reading and writing the EUI application when executing the LoRaWAN joins

Version 1.2.8263.21199 (16.08.2022)

- PORTAFID M3K V2 (027 12) device added
- Database update: once again possible without software update
- Release notes for database versions implemented

EX-TEC PM 5xx/400

- Firmware update: "su_gas.dat" file is updated at every firmware update

ATS 501/503

- Firmware updated (to Version 1.021)

Version 1.2.8084.16101 (18.02.2022)

EX-TEC PM 5xx/400

- Automatic download of adjustment files when reading device data set up
- History: Adjustment data for all user groups activated
- User rights: Reading of adjustment files enabled for all users
- History of adjustment files: "Save device data" button activated for connected and selected device
- History of adjustment files: Error when loading adjustment files from the database corrected

Read AQUAPHON® A 200 / SeCorr® C 200 / SeCorrPhon AC 200

- New firmware 2.006 available